

GROWTH STAGE	SEEDING	VEGETATIVE						BULB DEVELOPMENT		
										
DAS - Days After Sowing	10-18 DAS									
DAT - Days After Transplanting		4 DAT	11 DAT	16 DAT	23 DAT	31 DAT	33 DAT	44 DAT	51 DAT	
DOSAGE PER 16L TANKLOAD (The XANADU bottle cap holds approximately 25ml up to the topmost screw line)  = 25 ml										
	BASAL (Seedbed) (14-14-14) 20 Kg	400 ml	BASAL (46-0-0) + (14-14-14)	300 ml	TOP-DRESSING (46-0-0) + (14-14-14) + (16-20-0)	100 ml	TOP-DRESSING (46-0-0) + (0-0-60)			
				100 ml		300 ml		300 ml		
									100 ml	400 ml
NO. OF TANKLOADS		10 / Hectare		10 / Hectare		10 / Hectare		10 / Hectare	10 / Hectare	10 / Hectare
DOSAGE PER HECTARE										
	20 Kg T14	4L F1	50 Kg UREA 50 Kg T14	3L F1 1L F2	50 Kg UREA 50 Kg T14 50 Kg Ammophos	1L F1 3L F2	50 Kg UREA 50 Kg MOP	3L F2 1L F3	4L F3	
TOTAL REQT / HA: 8L F1 + 7L F2 + 5L F3										