

ZERO GRANULAR PROTOCOL FOR RICE [DIRECT-SEEDING METHOD]

GROWTH STAGE	SEEDLING		TILLERING		REPRODUCTIVE	HEADING
						
DAS - Days After Sowing	15-19 DAS	24-28 DAS	32-36 DAS	40-44 DAS	70-74 DAS	82-86 DAS
INTERVAL (Between Applications)		9 to 12 days	8 to 10 days	8 to 10 days	One month	12 to 14 days
DOSAGE PER 16L TANKLOAD (The XANADU bottle cap holds approximately 25ml up to the topmost screw line)  = 25 ml						
XANADU F1 MAXPOWER	200 ml	50 ml	50 ml			
			ADD DURING DRY SEASON:			
			 +100 ml			
XANADU F2 MAXPOWER			100 ml	200 ml		
				ADD DURING DRY SEASON:		
				 +100 ml		
XANADU F3 MAXPOWER					250 ml	250 ml
NO. OF TANKLOADS	5 / Hectare	10/ Hectare	10/ Hectare	10/ Hectare	10/ Hectare	10/ Hectare
DOSAGE PER HECTARE						
XANADU MAXPOWER	1L F1	500 ml F1	500 ml F1 + 1L F2	2 L F2	2.5L F3	2.5L F3
			ADD DURING DRY SEASON:			
BASE REQUIREMENT / HA: 2L F1 + 3L F2 + 5L F3			 +1L F1	 +1L F2		



REMINDER:

Follow the recommended increase in dosage if the weather is dry and the sunlight intensity is high during the TILLERING stage.