




MIXED FERTILIZER PROTOCOL FOR RICE [DIRECT-SEEDING METHOD]

GROWTH STAGE	SEEDLING		TILLERING		REPRODUCTIVE	HEADING
						
DAT - Days After Transplanting	15-19 DAS	24-28 DAS	32-36 DAS	40-44 DAS	70-74 DAS	82-86 DAS
INTERVAL (Between Applications)		9 to 12 days	8 to 10 days	8 to 10 days	One month	12 to 14 days
DOSAGE PER 16L TANKLOAD (The XANADU bottle cap holds approximately 25ml up to the topmost screw line)  = 25 ml						
XANADU F1 MAXPOWER	200 ml	BASAL RECOMMENDATION: UREA (46-0-0) 50 Kg + T14 (14-14-14) 50 Kg	100 ml			
XANADU F2 MAXPOWER				200 ml		
				ADD DURING DRY SEASON:  +100 ml		
XANADU F3 MAXPOWER					250 ml	250 ml
NO. OF TANKLOADS	5 / Hectare		10/ Hectare	10/ Hectare	10/ Hectare	10/ Hectare
DOSAGE PER HECTARE						
XANADU MAXPOWER	1L F1		1L F1	2 L F2	2.5L F3	2.5L F3
				ADD DURING DRY SEASON:  +1L F2		
BASE REQUIREMENT / HA: 2L F1 + 2L F2 + 5L F3						



REMINDER:

Follow the recommended increase in dosage if the weather is dry and the sunlight intensity is high at 40-44 DAT.